


1. SOFTWARE REGISTRATION

<http://support.prime-proof.com/register>

If you already have an account with us, please login using the [login page](#) and register your licenses by accessing the Licenses > Register License section.



Save time!
Register using your social network account!

First Name

Last Name

Email

Address

City

Country


ZIP

State (e.g. NY)

Company

Password

Re-type Password



Register license

Register a license X



Registration of your license is quite easy. Enter your 12-digit activation code that can be found on the licenche voucher that came with your product and click the 'Register' button.

If your product requires activation you can click the 'Activate' button right after you've registered. If your product requires an unlocking code the it will be sent to your e-mail address automatically after you have registered.

Activation code:



2. DOWNLOAD THE SOFTWARE



Prime Proof	Note	Mac	Win
Prime-Proof 5.0.0 (8358)			

3. ADDING PRINTER

▶ Printer has to be online ◀



Make your settings.

Most important:




Contone Proof	Hotfolder	Printer queue pre- settings	Paper Profile & Tuned Profile	Paper-Settings
---------------	-----------	--------------------------------	----------------------------------	----------------

4. ADDING JOB


click + in the top right of "Prime-Proof RIP"



make your settings in "Prime-Proof Layout"



click "Send" in the top right of "Prime-Proof Layout"



click "Send"

check your printer queue


Job-Warteschlange									
Job-Name	Medium	Warteschlange	Benutzer	Datum/Uhrzeit	Platten			Verarbeitung	Drukken
Prime-Proof Paper 51 204_17	Prime-Proof Paper SAT II	Pro 4900_Prime-Proof 247	Jens Kuhn	10.09.14 16:11	-	•		Fertig	OKB/OKB

► If the print job does not start please check the small icons (play/pause) on the top of the rows ◀



for certification print choose a color strip from the drop down menu in the top right of "Prime-Proof Layout"



import your measurement results by clicking "Measure" or "Messen" and "Next"



click "Next" at least 2 times




If everything is OK your certification print was successful.
If not, you have to do a Device-Link.




5. Device-Link


Right click on the printer queue and choose "Recalibrate Profile" or "Profil rekalisieren"



▼
Select the right settings



▼
Set a name for the tuned profile and print a target



▼
Import your measured values and click "Next"



▼
Check the values. If OK click "Finish".
If not OK click "Refine" and do an additional Device-Link.

